TradinSolutions EXECUTION LAYER

PLATFORM GUIDE

Signal copier: Telegram and Discord

Executes the calls from a Telegram or Discord channel you already follow on your own accounts, sized by your own settings, with every skipped call shown with its reason.

WORKS ON Telegram Discord MT4 MT5 cTrader Tradovate NinjaTrader

STARTER, PRO AND HEDGE

UPDATED 08 OCTOBER 2026

VIDEO · Episode 05 · Copying Telegram and Discord signals

01 What you'll have at the end
02 Before you start
03 Step by step
04 How a message is read
05 What each setting means
06 Worked example
07 Troubleshooting
08 FAQ

01

What you'll have at the end

A signal instance in the Cockpit that watches one Telegram or Discord channel you already follow and places its calls on the account or accounts you choose.

When the instance is running:

- Every new message in the channel is read and sorted into one of five kinds. Only new trade calls and updates to open trades can place or change an order.
- A call is read into instrument, direction, entry, stop and targets. Calls posted as images are read too.
- The size comes from your own settings on each destination, never from the lot size the channel posted.
- The filters and risk breakers you set on each destination are checked before the order goes out.
- A call the reader cannot parse, or is not sure enough of, is skipped and shown with its reason. Nothing is traded on a guess.

What it does not do:

- **TradinSolutions is a signal copier, not a signal provider.** It does not run, vet, rate or recommend any channel, and it does not sell signals. The relationship with the channel is yours. A poor channel executed accurately is still a poor channel.
- It does not make the call for you. It carries out the call the channel posted, inside the rules you set.
- It does not re-read a message after the channel edits it.

> **Important:** Automating a personal Telegram or Discord account is against those platforms' terms of service. You accept that risk when you connect a session, so use an account you are comfortable with.

02

Before you start

PLAN

The signal copier starts on Starter. Your plan sets how many **signal channels** you can run: Starter 1, Pro 3, Hedge 8. Telegram, Discord and TradingView share that one count, and one source feeding two accounts uses two. The free plan does not include the signal copier. Every paid plan has a 7-day free trial.

If an option is greyed out in the wizard, your plan's signal channel count is the usual reason.

WHAT TO HAVE READY

- **A connected broker account to trade on.** Connect it once under Accounts (Episode 02); it is then available to the copier, the signal copier and the journal. Start with a demo account. Every supported platform offers one.
- **For Telegram:** the phone number of the Telegram account that can see the channel, access to that account to receive the login code, and its two-step verification password if you have one set.
- **For Discord:** the user token of the Discord account that can see the channel.
- **Your risk numbers:** the risk per signal you want on each destination, and any daily limits your firm or your own plan sets.

> **Important:** A Telegram session gives access to the whole account: messages, contacts, everything. Your Discord user token works the same way. Never enter a login code, two-step password or token anywhere except the connection step inside the member app, and never share them with anyone, including people claiming to be support.

> **Note:** If you trade funded or challenge accounts, read your firm's current terms before you connect one, and ask the firm in writing when a clause is unclear.

US residents: MT4, MT5 and cTrader are not offered to US residents, so a US member can send signals only to futures accounts on Tradovate or NinjaTrader (Episode 07).

03

Step by step

CONNECT THE SESSION

1. Open **Accounts** and choose **+ Connect account**. Under "WHAT ARE YOU CONNECTING?", choose **Telegram** or **Discord**.
2. **Telegram:** enter your **PHONE NUMBER** and choose **Send the login code →**. Enter the **LOGIN CODE** Telegram sends you and choose **Verify →**. If your account has two-step verification on, enter your **TWO-STEP PASSWORD** and choose **Confirm →**.
3. **Discord:** paste the user token into **DISCORD USER TOKEN** and choose **Connect Discord →**.

The channels that account can see are resolved when it connects.

CREATE THE INSTANCE

4. Open the **Cockpit** and choose **+ New instance**.
5. **Source:** choose your Telegram or Discord session and the channel to watch. If you have not connected a session yet, choose **+ Authorise a new session instead** here. Then select **Choose destinations →**.
6. **Destinations:** select the account or accounts to trade on, then choose **Configure →**. Each extra account uses one more signal channel.
7. **Settings:** set sizing, entries, filters and risk breakers (see "What each setting means"). The AI trade manager is on by default.
8. Choose **Create and activate**. The app confirms "Instance created and armed." and the channel is watched from that moment.
9. Leave it on a demo destination through several sessions, including a volatile one, before you point it at a live or funded account. Compare what the channel posted with what was placed or skipped.

04

How a message is read

Every new message is classified into one of five kinds:

KIND	WHAT IT IS	CAN IT TRADE?
SIGNAL	A new trade call with a symbol and a direction	Yes
UPDATE	An instruction on an existing trade: move the stop, close half, close the trade	Yes
ANALYSIS	Commentary with nothing to act on	No
ADMIN	Greetings, promotions, results, links	No
NOISE	Everything else	No

A SIGNAL is then read into instrument, direction, entry, stop and targets. Image-only signals are read for the same fields. The size is worked out per destination from your settings.

EXAMPLE

A channel posts: "XAUUSD SELL NOW @ 2412, SL 2418, TP1 2406, TP2 2400". That reads as XAUUSD, sell at market, stop 2418, targets 2406 and 2400. At 1% risk on a 10,000 USD account the risk is 100 USD. The stop is 6.00 away, which is 600 USD per lot, so the size works out at about 0.16 lots.

ENTRY PRICES

With **Take market entries** on, a call to enter now is executed at market, with the posted price treated as a reference. With **Take limit and stop entries** on, a call that names a level the market has not reached is placed as a working order that waits for the price. **Give up on a working entry after** cancels it if it has not filled (default 120 minutes). The **Slippage limit** rejects calls the market has already moved away from.

UPDATES

With the **AI trade manager** in charge of open trades (the default), plain-language UPDATE messages after entry are acted on: moving a stop, closing a partial, or closing the trade. If you choose otherwise under **Who manages open trades**, updates are not executed and managing the open trade is left to you.

WHEN A CALL IS SKIPPED

- A call the reader cannot read is **skipped**, with the reason "could not parse".
- The reader gives each call a confidence score. A call below **Hold a call the reader is unsure of** (default 50) is skipped, with the reason.
- **Edited messages are not re-read.** If the channel changes a stop or entry by editing its post, the change is not picked up.

05

What each setting means

These are set per destination, so the same channel can trade differently on each account.

SETTING	WHAT IT DOES
Risk % per signal / Always the same lot	Sizing: a risk percentage worked out from the stop distance, or the same lot every time. The channel's own lot size is never used.
One entry / One leg per target	A single entry, or the entry split into one leg per take-profit level (up to 5).
Take market entries	Whether calls to enter at market are taken.
Take limit and stop entries	Whether calls to enter at a level are placed as working orders.
Slippage limit	Rejects a call when the price has moved too far from the posted entry.
Give up on a working entry after	Cancels a working entry that has not filled. Default 120 minutes.

SETTING	WHAT IT DOES
Entry-zone handling	How a call that gives an entry zone rather than a single price is entered.
Only take these	Only the instruments you list are traded. Anything else is skipped.
Only take calls from / until	Only calls that arrive inside these hours (UTC) are traded.
Ignore repeats within	A repeat of the same call inside this window is not traded twice. Default 10 minutes.
Skip around high-impact news	Skips new entries from 30 minutes before to 15 minutes after a high-impact release for the instrument's currencies. Closes and stop moves still go through.
Max trades a day	Once this many trades have been taken in the day, new calls are not taken.
Max loss a day	An amount in the account currency, measured as the 00:00 UTC balance minus equity now. Once it is reached, new calls are not taken.
Drawdown breaker	A percentage below the peak since the breaker was armed. Once tripped, it stays tripped until you save Risk breakers again.
Hold a call the reader is unsure of	The confidence threshold. Calls below it are skipped with the reason. Default 50.
Who manages open trades	Whether the AI trade manager acts on UPDATE messages. The AI trade manager is the default.

The trade copier's per-account limits (Episode 04) do not apply to signal destinations. A signal destination uses only the filters and risk breakers in this table.

WHY SIZE COMES FROM YOUR SETTINGS

A channel's "0.50 lots" on gold with a 6 USD stop is about 3% risk on a 10,000 USD account and 0.6% on a 50,000 USD account. Sizing each destination from its own settings and the stop distance removes that gap.

06

Worked example

Say you follow one gold channel and run two accounts: a 10,000 USD demo on MT5 that you use for testing, and a cTrader account on your own broker. One channel feeding two accounts uses two signal channels, so you are on Pro.

1. You connect both broker accounts under Accounts, then connect your Telegram session with **+ Connect account**.
2. You create the instance with **+ New instance**, choose your Telegram session and the channel, and select both accounts as destinations.
3. On the MT5 demo you set **Risk % per signal** at 1%, **Only take these** to XAUUSD, **Only take calls from / until** covering the hours you are usually at your desk, and **Max trades a day** at 3.
4. You leave the AI trade manager on, so "move SL to breakeven" and "close half" posts are carried out.

5. After **Create and activate**, you open **TUNE** on the cTrader destination, choose **PAUSE THIS DESTINATION** and save with **Save and apply**.

For two weeks you check the instance each evening. Most calls fill on the demo within your settings. One call is skipped as "could not parse", and one falls below the confidence threshold. One post is edited after you are filled, and the edit is not picked up. A call on EURUSD is skipped by **Only take these**. You can see each reason next to the message.

Only when the demo run looks the way you expect do you choose **RESUME THIS DESTINATION** on the cTrader destination, at a lower risk than the demo. Your stop still sits where the channel put it; gaps and slippage can still produce a larger loss than planned.

07

Troubleshooting

WHAT YOU SEE	LIKELY CAUSE	WHAT TO DO
The channel is not in the list	The connected Telegram or Discord account cannot see it	Join the channel with that account, then re-authorise the session so its channels are resolved again.
An option is greyed out in the wizard	Your plan's signal channel count	Remove an instance you no longer use, or check your plan on the pricing page.
A call was skipped as "could not parse"	The reader could not read it	Nothing is traded on a guess. Manage that call by hand if you want it.
A call was skipped as uncertain	It scored below Hold a call the reader is unsure of	Leave it, or change the threshold as a deliberate decision.
A call was skipped by a rule	Only take these, the time window, Ignore repeats within, the news window, Max trades a day, Max loss a day or the Drawdown breaker	The reason is logged with the call. Adjust the setting only if the rule did not do what you intended.
The symbol was not traded	Your broker names it differently or does not list it	Only prefix and suffix differences are matched automatically. Check the symbol in the call against your broker's name for it.
An edit to a post was not applied	Edited messages are not re-read	Manage that trade by hand.
An update ("move SL to BE") was not applied	The AI trade manager is not managing open trades, or the update could not be matched to an open trade	Check Who manages open trades, or manage that trade by hand.
Trades stopped after working for days	The session has ended. The Accounts row shows the "error" pill.	**Telegram:** re-authorise the session; it is repaired in place and keeps its channels. **Discord:** choose **REPLACE TOKEN**; its channels are kept.

A healthy signal instance shows "listening · last message ..." in the Cockpit. Channels are read every 45 seconds.

08

FAQ

Is TradinSolutions a signal service? No. It executes calls from channels you choose. It does not sell signals, manage accounts or give investment advice, and it does not vet or recommend channels.

Is it against Telegram's or Discord's rules? Automating a personal Telegram or Discord account is against those platforms' terms of service. You accept that risk by connecting a session. Use an account you are comfortable with.

Do I need to keep my computer or phone on? No. The relay is hosted, so nothing needs to run on your machine.

Can I follow different channels on different accounts? Yes. Each channel is its own instance with its own destinations and settings. Every source-to-account pair uses one of your plan's signal channels.

The channel posts a lot size. Why does my account trade a different one? Size comes from your settings on each destination, never from the channel's lot size.

What if the channel posts an entry the market has not reached yet? With Take limit and stop entries on, it is placed as a working order that waits for the price, and Give up on a working entry after cancels it if it does not fill.

Can I send channel calls to a futures account? Yes, with a contract rule for that destination (Episode 07). Calls with no rule are skipped and logged. A futures account takes one signal source only: the wizard refuses a second one.

Can I test it without risking money? Yes. Use a demo destination. It runs the whole path: reading, sizing, the order and the log.

Need help? Help centre: help.tradinsolutions.com · Email: contact@tradinsolutions.com · Community: the TradinSolutions Discord (tradinsolutions.com/community).

Trading leveraged products carries a high level of risk and can result in the loss of all invested capital. These tools execute and manage the decisions you make; they do not make trades profitable and are not investment advice. Test every setting on a demo account first. CFD products are not offered to United States residents.